



Heat Stress

High temperatures and humidity stress the body's ability to cool itself, and heat illness becomes a special concern during hot weather. There are three major forms of heat illnesses: **heat cramps**, **heat exhaustion**, and **heat stroke**, with heat stroke being a life threatening condition.

Heat Cramps

Heat cramps are muscle spasms which usually affect the arms, legs, or stomach. Frequently they don't occur until sometime later after work, at night, or when relaxing. Heat cramps are caused by heavy sweating, especially when water is replaced by drinking, but not salt or potassium. Although heat cramps can be quite painful, they usually don't result in permanent damage. To prevent them, drink electrolyte solutions such as Gatorade during the day and try eating more fruits like bananas.

Heat Exhaustion



Heat exhaustion is more serious than heat cramps. It occurs when the body's internal air-conditioning system is overworked, but hasn't completely shut down. In heat exhaustion, the surface blood vessels and capillaries which originally enlarged to cool the blood collapse from loss of body fluids and necessary minerals. This happens when you don't drink enough fluids to replace what you're sweating away.

The symptoms of heat exhaustion include: headache, heavy sweating, intense thirst, dizziness, fatigue, loss of coordination, nausea, impaired judgment, loss of appetite, hyperventilation, tingling in hands or feet, anxiety, cool moist skin, weak and rapid pulse (120-200), and low to normal blood pressure.

Somebody suffering these symptoms should be moved to a cool location such as a shaded area or air-conditioned building. Have them lie down with their feet slightly elevated. Loosen their clothing, apply cool, wet cloths or fan them. Have them drink water or electrolyte drinks. Try to cool them down, and have them checked by medical personnel. Victims of heat exhaustion should avoid strenuous activity for at least a day, and they should continue to drink water to replace lost body fluids.

Heat Stroke

Heat stroke is a life threatening illness with a high death rate. It occurs when the body has depleted its supply of water and salt, and the victim's body temperature

risers to deadly levels. A heat stroke victim may first suffer heat cramps and/or the heat exhaustion before progressing into the heat stroke stage, but this is not always the case. It should be noted that, on the job, heat stroke is sometimes mistaken for heart attack. It is therefore very important to be able to recognize the signs and symptoms of heat stroke - and to check for them anytime an employee collapses while working in a hot environment.

The early symptoms of heat stroke include a high body temperature (103 degrees F); a distinct absence of sweating (usually); hot red or flushed dry skin; rapid pulse; difficulty breathing; constricted pupils; any/all the signs or symptoms of heat exhaustion such as dizziness, headache, nausea, vomiting, or confusion, but more severe; bizarre behavior; and high blood pressure. Advance symptoms may be seizure or convulsions, collapse, loss of consciousness, and a body temperature of over 108° F.



It is vital to lower a heat stroke victim's body temperature. Seconds count. Pour water on them, fan them, or apply cold packs . Call 911 and get an ambulance on the way as soon as possible.

Anyone can suffer a heat illness, but by taking a few simple precautions, they can be prevented:

- Condition yourself for working in hot environments - start slowly then build up to more physical work. Allow your body to adjust over a few days.
- Drink lots of liquids. Don't wait until you're thirsty, by then, there's a good chance you're already on your way to being dehydrated. Electrolyte drinks are good for replacing both water and minerals lost through sweating. Never drink alcohol, and avoid caffeinated beverages like coffee and pop.
- Take a break if you notice you're getting a headache or you start feeling overheated. Cool off for a few minutes before going back to work.
- Wear light weight, light colored clothing when working out in the sun.
- Take advantage of fans and air-conditioners.

Get enough sleep at night. AWARENESS IS IMPORTANT

The key to preventing excessive heat stress is educating the employer and worker on the hazards of working in heat and the benefits of implementing proper controls and work practices. The employer should establish a program designed to acclimatize workers who must be exposed to hot environments and provide necessary work-rest cycles and water to minimize heat stress.

SPECIAL CONSIDERATIONS DURING PROLONGED HEAT SPELLS

During unusually hot weather conditions lasting longer than 2 days, the number of heat illnesses usually increases. This is due to several factors, such as progressive body fluid deficit, loss of appetite (and possible salt deficit), buildup of heat in living and work areas, and breakdown of air-conditioning equipment. Therefore, it is advisable to make a special effort to adhere rigorously to the above preventive measures during these extended hot spells and to avoid any unnecessary or unusual stressful activity. Sufficient sleep and good nutrition are important for maintaining a high level of heat tolerance. Workers who may be at a greater risk of heat illnesses are the obese, the chronically ill, and older individuals.

When feasible, the most stressful tasks should be performed during the cooler parts of the day (early morning or at night). Double shifts and overtime should be avoided whenever possible. Rest periods should be extended to alleviate the increase in the body heat load.

PREPARING FOR THE HEAT

One of the best ways to reduce heat stress on workers is to minimize heat in the workplace. However, there are some work environments where heat production is difficult to control, such as when furnaces or sources of steam or water are present in the work area or when the workplace itself is outdoors and exposed to varying warm weather conditions.

Humans are, to a large extent, capable of adjusting to the heat. This adjustment to heat, under normal circumstances, usually takes about 5 to 7 days, during which time the body will undergo a series of changes that will make continued exposure to heat more endurable.

On the first day of work in a hot environment, the body temperature, pulse rate, and general discomfort will be higher. With each succeeding daily exposure, all of these responses will gradually decrease, while the sweat rate will increase. When the body becomes acclimated to the heat, the worker will find it possible to perform work with less strain and distress.

Gradual exposure to heat gives the body time to become accustomed to higher environmental temperatures. Heat disorders in general are more likely to occur among workers who have not been given time to adjust to working in the heat or among workers who have been away from hot environments and who have gotten accustomed to lower temperatures. Hot weather conditions of the summer are likely to affect the worker who is not acclimatized to heat. Likewise, workers who return to work after a leisurely vacation or extended illness may be affected by the heat in the work environment. Whenever such circumstances occur, the worker should be gradually reacclimatized to the hot environment.

Drinking Water

In the course of a day's work in the heat, a worker may produce as much as 2 to 3 gallons of sweat. Because so many heat disorders involve excessive dehydration of the body, it is essential that



water intake during the workday be about equal to the amount of sweat produced. Most workers exposed to hot conditions drink less fluids than needed because of an insufficient thirst drive. A worker, therefore, should not depend on thirst to signal when and how much to drink. Instead, the worker should drink 5 to 7 ounces of fluids every 15 to 20 minutes to replenish the necessary fluids in the body. There is no optimum temperature of drinking water, but most people tend not to drink warm or very cold fluids as readily as they will cool ones.

Whatever the temperature of the water, it must be palatable and readily available to the worker. Individual drinking cups should be provided--never use a common drinking cup.

Heat acclimatized workers lose much less salt in their sweat than do workers who are not adjusted to the heat. The average American diet contains sufficient salt for acclimatized workers even when sweat production is high. If, for some reason, salt replacement is required, the best way to compensate for the loss is to add a little extra salt to the food. Salt tablets *should not* be used.

CAUTION

Persons with heart problems or those on a low sodium diet who work in hot environments should consult a physician about what to do under these conditions.

Protective Clothing

Clothing inhibits the transfer of heat between the body and the surrounding environment. Therefore, in hot jobs where the air temperature is lower than skin temperature, wearing clothing reduces the body's ability to lose heat into the air.

When air temperature is higher than skin temperature, clothing helps to prevent the transfer of heat from the air to the body. However, this advantage may be nullified if the clothes interfere with the evaporation of sweat.

In dry climates, adequate evaporation of sweat is seldom a problem. In a dry work environment with very high air temperatures, protective clothing could be an advantage to the worker. The proper type of clothing depends on the specific circumstance. Certain work in hot environments may require insulated gloves, insulated suits, reflective clothing, or infrared reflecting face shields. For extremely hot conditions, thermally conditioned clothing is available. One such garment carries a self-contained air conditioner in a backpack, while another is connected a compressed air source which feeds cool air into the jacket or coveralls through a vortex tube. Another type of garment is a plastic jacket which has pockets that can be filled with dry ice or containers of ice.

AWARENESS IS IMPORTANT

The key to preventing excessive heat stress is educating the employer and worker on the hazards of working in heat and the benefits of implementing proper controls and work practices. The employer should establish a program designed to acclimatize workers who must be exposed to hot environments and provide necessary work-rest cycles and water to minimize heat stress.

With a little caution and common sense, you can avoid heat illnesses.